Setting up socket.net (and other socket emails) on the Android Mail Application

(Please start at page 13 for editing existing accounts)

To begin, please navigate to the AndroidOS mail application.

Once there, please navigate to the section to create a new account.

You should then be sent to a screen which shows the following. As we will be setting up either an IMAP or POP3 account, you will click the “other” option.



This will then prompt you for the initial information for your account. Please type in both

your **full** email address, along with the password. After doing so, you will hit the button for “Manual Setup”. E.g. -



This will then ask if you would like to proceed with either an IMAP or POP3 account. Please check your current settings to verify which is correct for your account. For reference...

(IMAP is considered to be 'modern mail', with all of your emails being accessible across all devices)

(POP is an older version of mail, allowing you to download emails to your device. However, once these emails are downloaded, they are no longer accessible on other devices, or our webmail client)



This will then direct you to the “server settings” screen where we will take care of the server-side configuration of the mail client.

Please enter in the following information, depending on whether your account is either IMAP or POP3.

!!! IMPORTANT NOTE !!!
Note that if you are using a socket email which does not end with “@socket.net”, then you will have to set up the account using the same settings. However, any mention of “email” or “username” will be your FULL email address. E.g. - “Username = test@mvp.net”.

IMAP SETTINGS

Account:
Email address = Your FULL email address
Username = Your FULL email address
Password = Your current email password

Incoming Server:
IMAP server = mail.socket.net
Security type = SSL (or NONE according to selection below)
Port = 993 for SSL, or 143 for (non-SSL)
Imap path prefix = Leave as “optional”

Outgoing Server:
SMTP Server = mail.socket.net
Security type = SSL (or NONE according to selection below)
Port = 465 for SSL, or 587 for (non-SSL)

Require Authentication to send emails = This MUST be enabled to send mail
Your full email address and password should be listed below.

POP3 SETTINGS
Account:
Email address = Your FULL email address
Username = Your FULL email address
Password = Your current email password

Incoming Server:
IMAP server = mail.socket.net
Security type = SSL (or NONE according to selection below)
Port = 995 for SSL, or 110 for (non-SSL)
Auto-delete from server: Never

Outgoing Server:
SMTP Server = mail.socket.net

Security type = SSL (or NONE according to selection below)
Port = 465 for SSL, or 587 for (non-SSL)

Require Authentication to send emails = This MUST be enabled to send mail
Your full email address and password should be listed below.
Example (Using IMAP) -




3:25
5G
Server settings
Show password
Incoming server
IMAP server
mail.socket.net
Security type
SSL
Port
993
IMAP path prefix
Optional
Outgoing server
SMTP server
Next


3:26
5G
Server settings
Outgoing server
SMTP server
mail.socket.net
Security type
SSL
Port
465
Require authentication to send emails
webmailtest@socket.net
****
Show password
Next

Example using POP3 -




4:50
5G+
Server settings
Incoming server
POP3 server
mail.socket.net
Security type
SSL
Port
995
Auto delete from server
Never
Outgoing server
SMTP server
mail.socket.net
Done



From there, you will be asked for the mail sync period. Leaving this as defaults is perfectly fine.



You will then be asked to “Edit names”.
The account name refers to what you will see listed as the account in your mail app.
The “your name” refers to what people will see when you email them.
Example “Bob Jones <webmailtest@socket.net>”


3:26
5G
Edit names
Your account has been set up. You can now change your account name and the name that will appear on outgoing emails.
Account name (optional)
webmailtest@socket.net
Your name (for outgoing email)
webmailtest
Done

For editing EXISTING accounts...

Go to your existing account on your Android mail app and click the ‘menu’ icon at the top-left -



Then click the ‘setting’ icon of the new window that appears -



On the next screen, click on your account.



This will pop open a new window for your account. Go down to the ‘server settings’.



This will then open the server settings for your account.

Please go up to page 4 of the document to see the current selection for valid server options and proceed from there.

Congratulations! Your socket email is ready to go!